
Line-Stacker Documentation

Release beta

Jean-Baptiste Jolly

August 02, 2019

CONTENTS

1	LineStacker	3
1.1	main	3
1.2	line_image	4
1.3	OneD_Stacker	5
1.4	analysisTools	5
1.5	tools	8
2	Example	9
2.1	1D LineStacker	9
2.2	Cube LineStacker	10
3	Indices and tables	13
	Python Module Index	15
	Index	17

Line-Stacker is a new open access tool for stacking of spectral lines. Line-Stacker is an ensemble of both CASA tasks and native python tasks, and can stack both 3Dcubes or already extracted spectra. Additionally a set of tools are included to help further analyse stacked spectra and stacked sample.

Some example, showing how to use of Line-Stacker, can be found in the example section.

LINESTACKER

main

Library to stack interferometric images.

class `LineStacker.Coord` (*x, y, z=0, obsSpecArg=0, weight=1, image=0*)

Describes a stacking position on an image.

Class used internally to represent coordinates. May describe a physical coordinate or a pixel coordinate.

setWeightToX (*X, chanWidth=0*)
sets the weight of the image to X,

setZeroWeightLeft (*numberOfZeroLeftF, freqlen*)
function used to ignore spectral bins outside of the stacking spectral window

setZeroWeightRight (*numberOfZeroRightF, freqlen*)
function used to ignore spectral bins outside of the stacking spectral window

class `LineStacker.CoordList` (*imagenames=[], coord_type='physical', unit='rad'*)

Extended list to contain list of coordinates.

`LineStacker.getPixelCoords` (*coords, imagenames*)

Creates pixel coordinate list from a physical coordinate list and a list of images. :param coords: a list of stacker.Coord coordinates :param imagenames: a list of images' paths

`LineStacker.randomCoords` (*imagenames, ncoords=10*)

Randomize a set of coordinates anywhere on any images :param imagenames: a list of images paths :param ncoords: number of random coordinates

default is 10

`LineStacker.randomizeCoords` (*coords, beam, maxBeamRange=5*)

Randomize a new set of coordinates at a distance [beam, maxBeamRange*beam] of the original coordinates :param coords: list of original coordinates (stacker.Coord instances) :param beam: beam size is radians,

new random coordinates will be at a minimum distance beam from the original coordinates

Parameters **maxBeamRange** – maximum distance from original coordinates at which new coordinates can be located, in units of beams default is 5

`LineStacker.readCoords` (*coordfiles, unit='deg', lineON=True*)

Reads coordinate files from disk and produces a list. !To each image should be associated one single coord file. :param coordfiles: List of path to coordinate files. Files in csv format. x and y should

be in J2000. If using to stack line, redshift should be in the third column. A weight may be added in the last column to weight positions for mean stacking. If set to None stacking position is defined as the center of each cube

Parameters

- **unit** – Unit of input coordinates. Allows two values, ‘deg’ and ‘rad’.
- **lineON** – either True or False, should be set to True if doing line stacking default 0

`LineStacker.writeCoords(coordpath, coords, unit='deg')`

Write coordinates to a file

Parameters

- **coordpath** – absolute path to coordinate file to be created
- **coords** – list of coordinates (stacker.Coord instances) to write to file

line_image

`LineStacker.line_image.stack(coords, outfile='stackResult', stampsize=32, imagenames=[], method='mean', spectralMethod='z', weighting=None, maskradius=0, psfmode='point', primarybeam=None, fEm=0, chanwidth=30, plotIt=False, **kwargs)`

Performs line stacking in the image domain. returns: Estimate of stacked flux assuming point source.

Parameters

- **coords** – A coordList object of all target coordinates. outfile Target name for stacked image.
- **stampsize** – size of target image in pixels
- **imagenames** – Name of images to extract flux from.
- **method** – ‘mean’ or ‘median’, will determined how pixels are calculated
- **spectralMethod** – How to select the central frequency of the stack
The corresponding value should be found in the 3rd column of the coord file
possible methods are:
‘z’: the redshift of the observed line, additionally fEm (emission frequency) must be informed (as an argument of this Stack function)
‘centralFreq’: the (observed) central frequency, or velocity
‘channel’: to directly input the channel number of the center of the stack
- **weighting** – only for method ‘mean’, if set to None will use weights in coords.
- **maskradius** – allows blanking of centre pixels in weight calculation
- **psfmode** – Allows application of filters to stacking, currently not supported.
- **primarybeam** – only applies if weighting=‘pb’
- **fEm** – rest emission frequency of the line,
- **chanwidth** – number of channels of the resulting stack,
- **plotIt** – direct plot option

OneD_Stacker

`LineStacker.OneD_Stacker.Stack` (*Images*, *chansStack*='full', *method*='mean', *center*='lineCenterIndex', *velOrFreq*='vel')

Main (one dimensional) stacking function requires list of Image objects :param Images: list of images, images have to be objects of the Image class (`LineStacker.OneD_Stacker.Image`) :param chansStack: number of channels to stack

set to 'full' to stack all channels from all images user input (int) otherwise

Parameters

- **method** – stacking method, 'mean' and 'median' supported
- **center** – method to find central frequency of the stack, possible values are "center", to stack all spectra center to center, 'fit' to use gaussian fitting on the spectrum to determine line center 'zero_vel' to stack on velocity=0 bin 'lineCenterIndex' use the line center initiated with the image directly defined by the user (int)
- **velOrFreq** – 'vel' or 'freq', frequency or velocity mode

analysisTools

`LineStacker.analysisTools.bootStraping_Cube` (*coords*, *outfile*, *stampsize*=32, *imagenames*=[], *method*='mean', *weighting*=None, *maxmaskradius*=0, *fEm*=0, *chanwidth*=30, *nRandom*=1000, *save*='amp')

Performs bootstrapping stack of cubes, see `stacker.line_image.stack` for further information on stack parameters

Parameters

- **coords** – A `stacker.coordList` object of all target coordinates
- **outfile** – Target name for stacked image
- **stampsize** – size of target image in pixels
default is 32
- **imagenames** – Name of images to extract cubes from
- **method** – stacking method, 'mean' or 'median'
default is 'mean'
- **weighting** – weighting method to use if stacking method is mean
possible values are 'sigma2', 'sigma2F', '1/A', 'None', 1 or user input (float)
see `stacker.line-image` for a complete description of weighting methods
default is None
- **maskradius** – radius of the mask used to blank the centre pixels in weight calculation
default is 0
- **fEm** – rest emission frequency of the line
- **chanwidth** – number of channels of the resulting stack

- **nRandom** – number of bootstrap iterations
default is 1000
- **save** – data to save at each bootstrap iterations
possible values are ‘all’, ‘amp’ and ‘ampAndWidth’
‘all’ saves the full stack at each bootstrap iteration /!caution, can be memory expensive
‘amp’ saves the amplitude (maximum value of the stack) of the line, at each bootstrap iteration, fastest
‘ampAndWidth’ fits the line with a gaussian and saves the corresponding amplitude and width at each bootstrap iteration, can be cpu expensive
‘ouflow’ fits the line with two gaussian components and saves the stack parameters at each bootstrap iteration, can be cpu expensive
for ‘amp’, ‘ampAndWidth’ and ‘ouflow’ the line is obtained by summing all pixels inside the stack stamp
default is ‘all’

```
LineStacker.analysisTools.bootstraping_OneD (Images, nRandom=1000, chansStack='full',  
                                              method='mean', center='z', velOrFreq='vel', save='all')
```

Performs bootstrapping stack of spectra, see `stacker.OneD_Stacker.stack` for further information on stack parametres

Parameters

- **Images** – a list of `stacker.OneD_Stacker.Images`
- **nRandom** – number of bootstrap iterations
default is 1000
- **chansStack** – number of channels to stack, either a fixed number or ‘full’ for entire spectra
default is ‘full’
- **method** – stacking method, ‘mean’ or ‘median’
default is ‘mean’
- **center** – method to center spectra
possible values are ‘z’, ‘fit’, ‘zero_vel’, ‘center’ or user input (must be int)
see `stacker.OneD_Stacker.stack` for further information on centering methods default is ‘z’
- **velOrFreq** – velocity or frequency mode (chosed according to your spectral axis type)
possible values are ‘vel’ or ‘freq’
default is ‘vel’
- **save** – data to save at each bootstrap iterations
possible values are ‘all’, ‘amp’ and ‘ampAndWidth’
‘all’ saves the full stack at each bootstrap iteration /!caution, can be memory expensive
‘amp’ saves the amplitude of the line (maximum value of the stack) at each bootstrap iteration, fastest

‘ampAndWidth’ fits the line with a gaussian and saves the corresponding amplitude and width at each bootstrap iteration, can be cpu expensive
default is ‘all’

`LineStacker.analysisTools.randomizeCoords` (*coords*, *beam*=0, *lowerLimit*=‘default’, *upperLimit*=‘default’)

Function to randomize stacking coordinates, new random position uniformly randomized, centered on the original stacking coordinate

Parameters **coords** – A coordList object of all target coordinates. **beam**
beam size, used for default values of random range

lowerLimit Lower spatial limit (distance from stacking position) to random new random position.

Default is 5 beams

upperLimit Upper spatial limit (distance from stacking position) to random new random position.

Default is 10 beams

`LineStacker.analysisTools.rebin_CubesSpectra` (*coords*, *imagenames*, *regionSize*=False, *widths*=False)

Rebin a list of image-cubes so that all width have the same width as the smallest width !Lines must be visible before stacking to operate rebinning !Only one coord per image is necessary for rebinning

Parameters

- **coords** – A coordList object of all target coordinates.
- **imagenames** – Name of images to rebin
- **regionSize** – size (in pixels) to extract the spectra from if set to False, spectra will be extracted solely from the coord pixel
- **widths** – widths of the lines if set to ‘False’ the spectra will be fitted with a gaussian to extract the width

`LineStacker.analysisTools.rebin_OneD` (*images*)

Rebin a list of images so that all width have the same width as the smallest width !Lines must be visible before stacking to operate rebinning

Parameters **images** – A list of `stacker.OneD_Stacker.images`

`LineStacker.analysisTools.stack_estimator` (*coords*, *nRandom*=100, *imagenames*=[], *stampsize*=1, *method*=‘mean’, *chanwidth*=30, *lowerLimit*=‘default’, *upperLimit*=‘default’, ***kwargs*)

Performs stacks at random positions a set number of times. Allows to probe the relevance of stack through stacking random positions as a Monte Carlo process

returns: Estimate of stacked flux assuming point source.

Parameters

- **coords** – A coordList object of all target coordinates. **nRandom**

Number of iterations

- **imagenames** – Name of imagenames to stack
- **stampsize** – Size of the stamp to stack (because only the central pixel is extracted anyway, this should be kept to default to enhance efficiency)
- **method** – Method for stacking, see `LineStacker.line_image.stack`
- **chanwidth** – Number of channels in the stack

Lower spatial limit (distance from stacking position) to random new random position.

Default is 5 beams

upperLimit Upper spatial limit (distance from stacking position) to random new random position.

Default is 10 beams

`LineStacker.analysisTools.subsample_OneD(images, nRandom=10000, maxTest=<function maximizeSNR>, **kwargs)`

Randomly resamples spectra and grades them accordingly to a given grade function

Parameters

- **images** – A list of `stacker.OneD_Stacker.images`
- **nRandom** – Number of iterations of the Monte-Carlo process
- **maxTest** – function test to grade the sources build your own, or use existing: `maximizeAmp`, `maximizeSNR`, `maximizeOutflow`
- **other argument for `LineStacker.OneD_Stacker.Stack`** (*Any*) –

tools

`LineStacker.tools.ProgressBar(n, total)`

show progress of a process :param n: current step :param total: total number of steps

EXAMPLE

All examples presented bellow, as well as the example data sets used to execute them, are provided in LineStacker/Example

1D LineStacker


Basic usage

One dimensional example use of Line-Stacker

```
#This files shows basic examplpe use of
#one dimmensional stacking with LineStacker
import numpy as np
import LineStacker.OneD_Stacker

#In this example we stack 100 spectra that are located in the data folder
#and are named spectra_'+str(i) for i in range(100),
#the lines are identified with a central velocity, which can be found in the file 'data/central_velocity_'+str(i)
#lines can be idenfified in many ways however, see LineStacker.OneD_Stacker.Stack for more information
numberOfSpectra=100
allImages=([0 for i in range(numberOfSpectra)])
for i in range(numberOfSpectra):
    tempSpectra=np.loadtxt('data/spectra_'+str(i))
    tempCenter=np.loadtxt('data/central_velocity_'+str(i))
    #initializing all spectra as Image class, this is necessary to use OneD_Stacker.Stack
    allImages[i]=LineStacker.OneD_Stacker.Image(spectrum=tempSpectra, centralVelocity=tempCenter)
stacked=LineStacker.OneD_Stacker.Stack(allImages)
```

With a resulting plot looking like this:



Cube LineStacker

Basic usage


```
import LineStacker
import LineStacker.line_image

#coordinates files are selected using the GUI
coordNames=LineStacker.readCoordsNamesGUI()
coords=LineStacker.readCoords(coordNames)


#image names are identical to coordinates files, with '.image' replacing '_coords.txt'
imagenames=([coord.strip('_coords.txt')+'.image' for coord in coordNames])

#because redshift is used to identify the line center, the emission frequency is also provided
stacked=LineStacker.line_image.stack(    coords,
                                         imagenames=imagenames,
                                         fEm=1897420620253.1646,
                                         stampsize=16)
```

Here the GUI is used to select the coordinates files, it looks like this:



The above lines produce a stacked cube who that can be viewed with the “viewer” task in CASA:



INDICES AND TABLES

- `genindex`
- `modindex`
- `search`

I

LineStacker, 3
LineStacker.analysisTools, 5
LineStacker.line_image, 4
LineStacker.OneD_Stacker, 5
LineStacker.tools, 8

B

bootStraping_Cube() (in module LineS-
tacker.analysisTools), 5
bootstraping_OneD() (in module LineS-
tacker.analysisTools), 6

C

Coord (class in LineStacker), 3
CoordList (class in LineStacker), 3

G

getPixelCoords() (in module LineStacker), 3

L

LineStacker (module), 3
LineStacker.analysisTools (module), 5
LineStacker.line_image (module), 4
LineStacker.OneD_Stacker (module), 5
LineStacker.tools (module), 8

P

ProgressBar() (in module LineStacker.tools), 8

R

randomCoords() (in module LineStacker), 3
randomizeCoords() (in module LineStacker), 3
randomizeCoords() (in module LineS-
tacker.analysisTools), 7
readCoords() (in module LineStacker), 3
rebin_CubesSpectra() (in module LineS-
tacker.analysisTools), 7
rebin_OneD() (in module LineStacker.analysisTools), 7

S

setWeightToX() (LineStacker.Coord method), 3
setZeroWeightLeft() (LineStacker.Coord method), 3
setZeroWeightRight() (LineStacker.Coord method), 3
stack() (in module LineStacker.line_image), 4
Stack() (in module LineStacker.OneD_Stacker), 5
stack_estimator() (in module LineStacker.analysisTools),
7

subsample_OneD() (in module LineS-
tacker.analysisTools), 8

W

writeCoords() (in module LineStacker), 4